

# Setting up the IVS (Imaging Virtual Server)

## Guide for Networking Imaging with FileWave

The following steps will assist you in the setup and implementation of your Imaging Virtual Server (IVS)

If you already have your Imaging sever up and running please look at these guides for how to image [Windows](#) devices.

\*Please note: This document assumes you have already set up your FileWave Management Server.

Prepare and download all needed parts

Before starting be sure you have:

- Downloaded the latest Imaging Virtual Server (IVS) [linked here](#)
- A running FileWave server with clients enrolled (or with placeholders)
- FileWave Admin installed on your workstation
- Valid MAC Address for each Windows machine
- Virtual Environment (e.g. ESXI, Virtualbox, VMware Fusion)
- No Firewall between your VLANS or access to the Inter-VLAN Firewall to open Ports specified below

### IVS v5 capabilities:

- UEFI compatibility
- Multiple partitions per image
- GBT and MBR disks can be imaged
- Image a blank disk
- Windows 7, 8, 8.1, 10 (including non-UEFI, UEFI with CSM and native UEFI machines)
- Multiple netboot servers allowed on the network
- Option boot to select FileWave netboot server
- Check if the Windows partition is in hibernated or fast restart state before creating master image
- Imaging logs are now copied to IVS in order to ease imaging issues troubleshooting

## Network Considerations

### Subnets

The FileWave Imaging appliance has to be configured as an “ip-helper” on your switches so it can receive and answer BOOTP requests from your clients.

The FileWave network imaging solution is unicast so there will need to be some preparation on your end if you intend to image across multiple subnets. The two options will be:

1. Install a separate FileWave Imaging Virtual Server (IVS) on each subnet you plan to image from and connect them all to the FileWave server by following the "Connecting IVS to FileWave Server" section in this document.
2. Setup "Helper IPs" on your layer 3 devices (e.g. routers, routing switches) that will point the broadcast requests for PXE and Netbooting to your single FileWave IVS. Once this has been completed you will need to make a change on the IVS. To do this either open the console for this server in your virtual environment or ssh into the server with Putty (Windows) or terminal (macOS):
  1. Open terminal (If on Windows you can use Putty [linked here](#) and use the credentials root/filewave (FileWave 15.4.2 and below) or fwadmin/filewave (FileWave 15.5.0 and beyond) then skip to step 3 below)
  2. Type in the following command


```
# replace IVS-IP-Address with your IP address
$ ssh root@IVS-IP-Address
```

when prompted for a password use: filewave

3. 

```
# enter in imaging-control subnet add to add your subnet addresses
$ imaging-control subnet add
```

4. This will prompt for a valid IP address from the subnet and subnet mask  
Note: use command imaging-control subnet remove to remove a subnet



## Firewall

The IVS needs to be able to connect to your FileWave Server on the following Ports

- 20017
- 20443
- 20445

Any client(s) subnets where imaging should work must be able to reach the following Ports on the IVS:

- 67 (DHCP), 69 (TFTP), 80 (HTTP), and 20444 (HTTPS)
- Ports 111 (TCP,UDP) and 20490 (TCP,UDP) are used for VPN to NFS access

**i** Prior to FileWave 15.5.0 port 2049 TCP/UDP was used for a client to reach the NFS mount, but with 15.5.0 a VPN connection is made on 20490 TCP/UDP and then allows access to the mount.

Any machine running FileWave Central needs to be able to connect to your IVS on the following Ports:

- 20010 (Client Monitor), 20444 (Remote Configuration, Shared Keys)

The FileWave Server must be able to reach the IVS on port 20444 for On-Premise customers.

**i** Note that if you are a FileWave Hosted customer then you need to review this article: [FileWave Hosted Servers and IVS Setup](#)

## Starting the Imaging Appliance for the first time:

1. Download the latest Imaging Virtual Server (IVS) [linked here](#)
2. Import the Imaging Virtual Appliance (IVS) into your virtual environment or use a player to start up the machine. Note: If you need help on this please use the help guide [linked here](#)
3. If v.15.5+ Please see: [Setting the Password on First Login to FileWave Appliances \(15.5+\)](#)

4. When the server starts up it will display the IP address, be sure to make a note of this. Should the machine get stuck during boot, showing a white bar at the bottom please send a CTRL-ALT-DEL to the machine. The second boot should be much quicker.
5. You should log into the machine (either console or SSH) and change the default password from what is currently filewave to your own.
  1. Open terminal (If on Windows you can use Putty [linked here](#) and use the credentials root/filewave then skip to step 3 below)
  2. Type in the following command


```
# replace IVS-IP-Address with your IP address
$ ssh root@IVS-IP-Address
```

when prompted for a password use: filewave

3. Then type the command below to enter your new password

```
$ passwd
```

4. Enter new password



The screenshot shows a terminal window titled 'Tony — root@imaging-appliance:~ — ssh root@10.1.3.243 — 95x17'. The terminal output is as follows:

```
[root@imaging-appliance ~]# passwd
Changing password for user root.
New password:
Retype new password:
passwd: all authentication tokens updated successfully.
[root@imaging-appliance ~]#
```

Next, change the IP of the IVS to a static IP.

1. Locate Network Interface:

First, identify the network interface you wish to configure. You can list all network interfaces using:

```
networkctl list
```

```
admin@ip-172-30-3-220:/etc/network$ networkctl list
IDX LINK TYPE      OPERATIONAL SETUP
---
 1 lo    loopback  carrier    unmanaged
 2 ens5  ether     routable   configured

2 links listed.
```

2. Edit the /etc/network/interfaces file: Using 'nano', edit the interfaces file to set the network configurations.

```
nano /etc/network/interfaces
```

Your default interfaces file should look something like this (your interface name may be different):

```
# The loopback network interface
auto lo eth0
iface lo inet loopback
```

```
# The primary network interface
iface eth0 inet dhcp
```

Change the file to look like this, using your network preferences (note 'dhcp' has been changed to 'static' in line 6)

```
# The loopback network interface
auto lo eth0
iface lo inet loopback

# The primary network interface
iface eth0 inet static
address 192.168.10.33
netmask 255.255.255.0
gateway 192.168.10.255
dns-nameservers 192.168.10.254 192.168.10.255
```



3. Verify Resolv.conf, hosts and hostname files: Verify that these files in /etc/ are configured correctly for your network and server. /etc/resolv.conf: This file should list your DNS servers

/etc/hosts: This file should point your FQDN to localhost (127.0.0.1) - Below is an example of what the file looks like on ivs1.filewave.net for example. Notice the 2 entries for loopback. Although IPv6 should be disabled, it is good to include the IPv6 loopback in case it is ever enabled.

```
127.0.0.1      localhost
::1           localhost ip6-localhost ip6-loopback
ff02::1       ip6-allnodes
ff02::2       ip6-allrouters
127.0.0.1     ivs1.filewave.net
::1           ivs1.filewave.net
```

/etc/hostname: Specifies the hostname for your server. This is filewave by default.

4. Disable IPv6: Edit the sysctl.conf file by adding the following lines to the end of the file:

```
nano /etc/sysctl.conf
```

```
net.ipv6.conf.all.disable_ipv6 = 1
net.ipv6.conf.default.disable_ipv6 = 1
net.ipv6.conf.lo.disable_ipv6 = 1
net.ipv6.conf.tun0.disable_ipv6 = 1
```

5. Restart/Check Network Status:

```
systemctl restart networking.service


systemctl status networking.service
```

6. Verify IP:


```
ip a
```

## Connecting IVS to the the FileWave Server:


1. Open and connect your FileWave Admin to your FileWave server
2. Open the preferences and go to the "Imaging" tab
3. Hit the "+" at the bottom left of the blank pane




4. Enter the IP address of the IVS into "Preference for Imaging"
5. Make sure the box marked "generate new key" is now checked and click "OK"



6. When the Imaging Monitor opens specify your FileWave Server Address and Port 20015. Confirm by clicking "Ok" to finish configuration of your IVS.



7. Restart the Imaging Virtual Server (IVS)
8. Open the preferences and go to the "Imaging" tab again
9. Select the server in the pane and click the status button below. Status lights should be all green with the exception of "NBI for macOS imaging:" (If there are more red lights and clicking the refresh button doesn't help, please contact support)



Congratulations, you have successfully set up and configured your FileWave Imaging server! You are now ready to image Windows devices.

## Related Content

- [FileWave Hosted Servers and IVS Setup](#)

