

# Components (PSImage)

PSImage is not supported by FileWave Support so please do not submit tickets with them about it. The information provided here is for educational purposes only. If you would like to purchase professional services hours for consulting assistance setting up PSImage or customizing it please contact [professional.services@filewave.com](mailto:professional.services@filewave.com) with your request. If you have existing unused professional services hours you may be able to use them for this purpose. Any feedback on PSImage can also be sent to the same email address. Any work on this would be done on [Discord](#) or in working with [Professional Services](#). For the official Windows Imaging solution please see [Network Imaging / IVS](#).

## 3 Phases of Disk Imaging



1. Boot Windows PE
2. Read psimage share info from config.ini
3. Mount psimage share

1. Erase & re-partition hard drive
2. Restore WIM image
3. Rebuild & hide recovery partition
4. Inject drivers for model
5. Copy files to hard drive & prep for post-imaging

1. Rename PC
2. Install FW client MSI
3. Add firewall exception
4. Import Wi-Fi profile if present
5. Run custom post-imaging actions (to\_do.bat)

When imaging over the network from the psimage network share there are 3 phases. The above diagram describes what happens during each phase and the info below describes which script is responsible for the actions during each phase.

1. Pre-imaging (x:\imaging\go.ps1) - Gets connection info from config.ini automatically or prompt user about server hosting SMB share and then connect to it
2. Imaging (z:\scripts\PSImage.ps1) - Capture or restore disk image
3. Post-imaging (z:\scripts\runonce.ps1) - Post-imaging actions like setting the computername, installing the FW client, adding client firewall exception, importing a Wi-Fi profile. There are 2 reboots.

## Pre-imaging Components in WinPE

boot.wim holds WinPE and is the imaging environment you're booting into to gain full access to the local hard drive. You'll learn how to build boot.wim later in [Building Your Imaging Environment](#). You can also find boot.wim in the sources folder in the WinPE partition of the USB thumb stick, as well as in your reimaging fileset and the WDS server (if you decide to use PXE). To edit it you must mount the boot.wim WIM image, make your edits, and commit your changes to unmount it. While mounted the contents are mapped to a folder you designate on the local drive. The following files reside in the boot.wim file in the \imaging folder.

- config.ini file - controls pre-imaging and imaging configuration
- go.ps1 - handles the pre-imaging logic/work
- password.txt - if present, password stored here is used by go.ps1 to gate the disk imaging and prevent unauthorized users from using PSImage

## Imaging/Post-imaging Components

The following folders are present on the psimage share for network imaging or the secondary Imaging volume on the USB thumb drive for local imaging. These are used during the imaging and post-imaging process. When booted into the WinPE imaging environment the psimage share or 2ndary volume of your dual-partitioned USB thumb drive is mapped to as the z: drive. WinPE itself is mounted as the x: drive.

- config - Add trigger files below as necessary
- image\_mappings.txt => lets you associate disk image and computer name to PC based on serial number. There must be one blank line at the end of this file. You can also set custom fields for client devices here.

- If debug.on exists then restore will drop to command prompt instead of rebooting for reviewing output and troubleshooting.
- If mode.reimage exists then move straight to restore and skip PSImage main menu without asking user whether to capture or restore. The only exception is if the assigned disk image for a device entry in image\_mappings.txt is set to the string "capture".
- server.dns => holds FQDN for FileWave server that will be used to update custom field for imaging to false to block a reimaging loop
- app.token => holds base64 app token used to flip custom field for imaging to false and to set custom fields specified in image\_mappings.txt when imaging via fileset
- edit\_config.ps1 => utility to display current config and set many of the above configurable options (except for image\_mappings.txt). Right click and pick "Run with PowerShell".
- extra
- All files/folders in this folder will be copied to c:\windows\temp\psimage on reimaged client device.
- If Wi-Fi.xml profile exists it will be copied to c:\windows\temp\psimage on reimaged client device and applied immediately during first post-imaging pass.
- fwclient
- Holds custom FW client MSI. Upload client using upload\_client.ps1. Right-click and "Run with PowerShell".
- If kiosk "custom" folder is present contents will be copied to client installation folder during post-imaging to apply kiosk customizations.
- images
- Captured images are uploaded here.
- image\_list.txt holds list of disk images and description to be displayed to user if no disk imaging assignment is present for PC. If you delete a disk image remember to remove its entry from this file. There must be a single blank line at the end of this file.
- logs
- history.log => All reimaging operations from this share/USB drive are logged here. There must be one blank line at the end of this file.
- Use search\_history.ps1 to search log file for specific restore operations. Right-click and "Run with PowerShell".
- restore => transcripts of each image restore operation are logged in this folder and named \_\_.log
- models
- Contains driver packs for computer models
- Use upload\_driver\_pack.ps1 to upload drivers for your computer models. Follow instructions in ReadMe.txt in the models folder for details.
- scripts
- The brains of PSImage. Do not modify any files here unless instructed to do so.
- If to\_do.bat exists it will be copied to c:\windows\temp\psimage. Will be run at end of the post-imaging process on client PC. Use this file to trigger any executables you may have included in the extra folder. These are run under the context of the fwadmin local administrator account. Note that psimage folder will be deleted at end of post-imaging along with the fwadmin account. In general try to deploy items as filesets if possible instead of using to\_do.bat if you can help it. However, if it's a task that must be done on the reimaged client PC ASAP and cannot wait for the deployment of a fileset then use to\_do.bat.
- sysprep
- unattend.xml sysprep answer file goes here
- Run prep\_ref\_vm.ps1 to prep reference VM for image capture, including adding temp fwadmin account and sysprepping using unattend.xml. fwadmin account will be deleted at end of post-imaging. Follow instructions in ReadMe.txt for details.
- import - contains importable filesets and custom fields used for imaging

## Other Misc Items

There are 2 spots with hidden options for troubleshooting. Enter "z" to drop to command line in imaging phase in WinPE at

1. Main PSImage menu and
2. When asked to press Return to reboot after successful image capture.

C:\Windows\Temp\restore.done created immediately before last reboot. Use this file in requirement scripts to postpone filesets until post-imaging is complete.

Beginning and ending imaging times are written to registry of reimaged client at HKLM\Software\PSImage. Name of image used to reimage PC is also written here. Custom field data specified in image\_mappings.txt will also be written here if the client device is reimaged using any other method besides via fileset.

Post-imaging log is written to c:\windows\temp\psimage.log on client device. If you don't end up at login prompt then check here to see where it failed as post-imaging process did not complete.

---

🕒Revision #9

★Created 21 July 2023 15:51:22 by Josh Levitsky

✍Updated 21 July 2023 16:33:48 by Josh Levitsky