


Microsoft Defender Compliance Pack (Win)

 Work in progress. Check back tomorrow (Feb 15) and we hope you will attend the Roadshow.

Description

This will be a guide to take FileWave usage one major step further than simply installing an application like Microsoft Defender. In this article you will see how to use Custom Fields, Smart Groups, Filesets, and Grafana to report on the status of your fleet. You can apply these ideas to other software solutions where you need to know if they are working, and to potentially fix them.

Ingredients

- FileWave Central
- [Microsoft Defender Recipe \(Win\)](#)
- [Defender Custom Fields.customfields](#)
- [Defender Update Defs \(Win\).fileset.zip](#)
- [Defender Run Scan \(Win\).fileset.zip](#)

The Problem

You are managing hundreds or thousands of macOS or Windows devices, and need to understand if your environment is secure. Today you have been told to deploy Microsoft Defender and to provide reporting to your CISO demonstrating that you have Anti-Malware protection in place, and that it is operating correctly.


- What kind of installers are used?
- How can the install be performed silently? Fileset Magic needed?
- What is the deadline to have the product deployed?
- Will it replace another product?
- MacOS, Windows or both?

Get started with this like any other deployment project:

- Ask the vendor for installation documentation - but FileWave may also post some examples;
- Create a reverse timeline. Start small.
- Search the Internet for how others have reported on that product because FileWave can do anything scriptable.

Test and Verify:

- Test. Test. Verify and then test again.
- Deploy to 1 machine, then expand in growing waves so that you can stay ahead of issues.
- Do you have an Early Adopters group of users who give feedback and are forgiving?




Deployment

Installers on Windows are usually an EXE or an MSI. In this case a BAT file is provided by Microsoft because Defender is part of Windows.

Did you know that you can execute scripts in Filesets, and each kind runs in a specific order and time?

How could the Uninstallation Scripts be helpful? Think about later when you may want to remove the deployed software.

For the Deployment phase see this article on installation: [Microsoft Defender Recipe \(Win\)](#)



The screenshot shows the 'QueryBuilder - Devices without Defender' interface. The 'Name' field is 'Devices without Defender' and the 'Main Component' is 'Desktop Device'. There is a checkbox for 'Include Archived Clients'. The 'Criteria' tab is active, showing a logical expression: 'All of these expressions must be true'. The first criterion is 'Custom Fields / Defender App Version is null'. The second criterion is 'One or more of these expressions must be true', which includes two sub-criteria: 'Not Operating System / OS Type is macOS' and 'Not Operating System / OS Type is Windows'.

Reporting

Queries/Reports are an easy way to keep track of progress and problems. We've made some Custom Fields for Defender, and we can leverage them to show who is missing Defender.


FileWave also has installed application reporting but depending on your needs and how that application reports itself you can consider either method.

To use the custom fields you will want to download [Defender Custom Fields.customfields](#) and then add them to your server. Do this in FileWave Central -> Assistants -> Custom Fields -> Edit Custom Field Definitions. Here you will click Import and then pick the file you downloaded. This file has fields that will work for both macOS and Windows. Once added you'll want to enable them for a couple of devices at first. To do that go to FileWave Central -> Clients and right click on a device and pick Edit Custom Field Associations. There you can check the boxes to enable these new fields. When you are happy with these Custom Fields, you'll want to go back to Edit Custom Field Definitions and pick "Assigned to all Devices" for each of the fields.

Custom Fields based on scripts always need to be tested.

Now that you have your Custom Fields in place you should have some results. You can see them by going to Clients -> Customize Columns in the Toolbar, and then adding a couple of the custom fields to just see their values. You could also double click on any device in Clients that has the field active and see the values on the Device Details tab.

Let's move on to making a Query in Central. Click the New Query button in the Toolbar. Ignore the copies of the field below with a "2" as this is my lab. Notice that I used "Defender Healthy" as a Custom Field to test if Defender is healthy. I want to make sure that the field is populated so I check that it's not null, and I want to find unhealthy so I'm going to look for devices where it is false.



The screenshot shows the 'QueryBuilder - Microsoft Defender Unhealthy' interface. The 'Name' field is 'Microsoft Defender Unhealthy' and the 'Main Component' is 'All Devices'. There is a checkbox for 'Include Archived Clients'. The 'Criteria' tab is active, showing a logical expression: 'All of these expressions must be true'. The first criterion is 'Custom Fields / Defender Healthy is not null'. The second criterion is 'Not Custom Fields / Defender Healthy equals false'.

To find devices missing Defender notice that the App Version Custom Field can be used. If it is null (empty) then there is no Defender installed.

Name: Main Component:

☐ Include Archived Clients

Criteria Fields

All of these expressions must be true

☐ Custom Fields / Defender App Version is null

One or more of these expressions must be true

☐ Not Operating System / OS Type is macOS

☐ Not Operating System / OS Type is Windows

Remediation

Dashboards

There are two parts to creating a dashboard, getting the data to the dashboard (Prometheus), displaying the data in the way you want (Grafana).

[yaml_dashboard_files.zip](#)

Create the dashboard:

Copy and Paste the JSON into a New dashboard:

▼ Dashboard JSON

```
{
  "annotations": {
    "list": [
      {
        "builtIn": 1,
        "datasource": {
          "type": "grafana",
          "uid": "-- Grafana --"
        },
        "enable": true,
        "hide": true,
        "iconColor": "rgba(0, 211, 255, 1)",
        "name": "Annotations & Alerts",
        "type": "dashboard"
      }
    ]
  },
  "editable": true,
  "fiscalYearStartMonth": 0,
  "graphTooltip": 0,
  "id": 19,
  "links": [],
  "liveNow": false,
  "panels": [
    {
      "collapsed": false,
      "gridPos": {
        "h": 1,
        "w": 24,
        "x": 0,
        "y": 0
      },
    }
  ]
}
```

```

        "id": 7,
        "panels": [],
        "title": "Overall Status",
        "type": "row"
    },
    {
        "datasource": {
            "type": "prometheus",
            "uid": "filewave_prometheus"
        },
        "description": "",
        "fieldConfig": {
            "defaults": {
                "color": {
                    "mode": "palette-classic"
                },
                "custom": {
                    "hideFrom": {
                        "legend": false,
                        "tooltip": false,
                        "viz": false
                    }
                },
                "mappings": [],
                "unitScale": true
            },
            "overrides": [
                {
                    "matcher": {
                        "id": "byName",
                        "options": "{__name__=\"filewave_inventory_query_55\",
genericclient_ptr__operating_system__type=\"OSX\", instance=\"localhost:20443\", job=\"extra-config-https\",
query_name=\"overall_os_breakdown\"}"
                    },
                    "properties": [
                        {
                            "id": "displayName",
                            "value": "macOS"
                        },
                        {
                            "id": "color",
                            "value": {
                                "fixedColor": "blue",
                                "mode": "fixed"
                            }
                        }
                    ]
                },
                {
                    "matcher": {
                        "id": "byName",
                        "options": "{__name__=\"filewave_inventory_query_55\",
genericclient_ptr__operating_system__type=\"WIN\", instance=\"localhost:20443\", job=\"extra-config-https\",
query_name=\"overall_os_breakdown\"}"
                    },
                    "properties": [
                        {
                            "id": "displayName",
                            "value": "Windows"
                        },
                        {
                            "id": "color",
                            "value": {
                                "fixedColor": "light-purple",
                                "mode": "fixed"
                            }
                        }
                    ]
                }
            ]
        }
    }
]

```

```
    },
    "gridPos": {
      "h": 10,
      "w": 5,
      "x": 0,
      "y": 1
    },
    "id": 10,
    "links": [
      {
        "targetBlank": true,
        "title": "",
        "url": "https://support2.filewave.net/filewave/reports/55/overview/"
      }
    ],
    "options": {
      "legend": {
        "displayMode": "list",
        "placement": "bottom",
        "showLegend": true
      },
      "pieType": "pie",
      "reduceOptions": {
        "calcs": [
          "lastNotNull"
        ],
        "fields": "",
        "values": false
      },
      "tooltip": {
        "mode": "single",
        "sort": "none"
      }
    },
    "targets": [
      {
        "datasource": {
          "type": "prometheus",
          "uid": "filewave_prometheus"
        },
        "editorMode": "builder",
        "exemplar": false,
        "expr": "filewave_inventory_query_55",
        "instant": true,
        "legendFormat": "{{defender_healthy_fwcomp_pack}}",
        "range": false,
        "refId": "A"
      }
    ],
    "title": "Overall Desktop Device Breakdown",
    "type": "piechart"
  },
  {
    "datasource": {
      "type": "prometheus",
      "uid": "filewave_prometheus"
    },
    "description": "",
    "fieldConfig": {
      "defaults": {
        "color": {
          "mode": "palette-classic"
        },
        "custom": {
          "hideFrom": {
            "legend": false,
            "tooltip": false,
            "viz": false
          }
        }
      }
    },
  },
```

```
    "mappings": [],
    "unitScale": true
  },
  "overrides": [
    {
      "matcher": {
        "id": "byName",
        "options": "{__name__=\"filewave_inventory_query_56\",
genericclient_ptr__operating_system__type=\"OSX\", instance=\"localhost:20443\", job=\"extra-config-https\",
query_name=\"devices_without_defender\"}"
      },
      "properties": [
        {
          "id": "displayName",
          "value": "macOS"
        }
      ]
    },
    {
      "matcher": {
        "id": "byName",
        "options": "{__name__=\"filewave_inventory_query_56\",
genericclient_ptr__operating_system__type=\"WIN\", instance=\"localhost:20443\", job=\"extra-config-https\",
query_name=\"devices_without_defender\"}"
      },
      "properties": [
        {
          "id": "displayName",
          "value": "Windows"
        }
      ]
    }
  ],
  "gridPos": {
    "h": 10,
    "w": 5,
    "x": 5,
    "y": 1
  },
  "id": 11,
  "links": [
    {
      "targetBlank": true,
      "title": "",
      "url": "https://support2.filewave.net/filewave/reports/56/overview/"
    }
  ],
  "options": {
    "legend": {
      "displayMode": "list",
      "placement": "bottom",
      "showLegend": true
    },
    "pieType": "pie",
    "reduceOptions": {
      "calcs": [
        "lastNotNull"
      ],
      "fields": "",
      "values": false
    },
    "tooltip": {
      "mode": "single",
      "sort": "none"
    }
  },
  "targets": [
    {
      "datasource": {
```

```

        "type": "prometheus",
        "uid": "filewave_prometheus"
    },
    "editorMode": "builder",
    "exemplar": false,
    "expr": "filewave_inventory_query_56",
    "instant": true,
    "legendFormat": "{{defender_healthy_fwcomp_pack}}",
    "range": false,
    "refId": "A"
}
],
"title": "Devices without Defender",
"type": "piechart"
},
{
    "datasource": {
        "type": "prometheus",
        "uid": "filewave_prometheus"
    },
    "description": "Relative health of Microsoft Defender",
    "fieldConfig": {
        "defaults": {
            "color": {
                "mode": "palette-classic"
            },
            "custom": {
                "hideFrom": {
                    "legend": false,
                    "tooltip": false,
                    "viz": false
                }
            },
            "mappings": [],
            "unitScale": true
        },
        "overrides": [
            {
                "matcher": {
                    "id": "byName",
                    "options": "True"
                },
                "properties": [
                    {
                        "id": "color",
                        "value": {
                            "fixedColor": "green",
                            "mode": "fixed"
                        }
                    }
                ]
            },
            {
                "matcher": {
                    "id": "byName",
                    "options": "False"
                },
                "properties": [
                    {
                        "id": "color",
                        "value": {
                            "fixedColor": "semi-dark-red",
                            "mode": "fixed"
                        }
                    }
                ]
            }
        ]
    },
    "gridPos": {

```

```
    "h": 10,
    "w": 5,
    "x": 10,
    "y": 1
  },
  "id": 1,
  "links": [
    {
      "targetBlank": true,
      "title": "",
      "url": "https://support2.filewave.net/filewave/reports/49/overview/"
    }
  ],
  "options": {
    "legend": {
      "displayMode": "list",
      "placement": "bottom",
      "showLegend": true
    },
    "pieType": "pie",
    "reduceOptions": {
      "calcs": [
        "lastNotNull"
      ],
      "fields": "",
      "values": false
    },
    "tooltip": {
      "mode": "single",
      "sort": "none"
    }
  },
  "targets": [
    {
      "datasource": {
        "type": "prometheus",
        "uid": "filewave_prometheus"
      },
      "editorMode": "builder",
      "exemplar": false,
      "expr": "filewave_inventory_query_49{defender_healthy_fwcomp_pack=\"True\"}",
      "instant": true,
      "legendFormat": "{{defender_healthy_fwcomp_pack}}",
      "range": false,
      "refId": "A"
    },
    {
      "datasource": {
        "type": "prometheus",
        "uid": "filewave_prometheus"
      },
      "editorMode": "builder",
      "expr": "filewave_inventory_query_49{defender_healthy_fwcomp_pack=\"False\"}",
      "hide": false,
      "legendFormat": "{{defender_healthy_fwcomp_pack}}",
      "range": true,
      "refId": "B"
    }
  ],
  "title": "Defender Healthy?",
  "type": "piechart"
},
{
  "datasource": {
    "type": "prometheus",
    "uid": "filewave_prometheus"
  },
  "fieldConfig": {
    "defaults": {
      "color": {
```



```
    "mode": "thresholds"
  },
  "custom": {
    "align": "auto",
    "cellOptions": {
      "type": "auto"
    },
    "filterable": false,
    "inspect": false
  },
  "mappings": [],
  "thresholds": {
    "mode": "absolute",
    "steps": [
      {
        "color": "green",
        "value": null
      },
      {
        "color": "red",
        "value": 80
      }
    ]
  },
  "unitScale": true
},
"overrides": [
  {
    "matcher": {
      "id": "byName",
      "options": "__name__"
    },
    "properties": [
      {
        "id": "custom.width",
        "value": 290
      },
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "Time"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "instance"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
```

```
        "options": "query_name"
    },
    "properties": [
        {
            "id": "custom.hidden",
            "value": true
        }
    ]
},
{
    "matcher": {
        "id": "byName",
        "options": "Value"
    },
    "properties": [
        {
            "id": "custom.hidden",
            "value": true
        }
    ]
},
{
    "matcher": {
        "id": "byName",
        "options": "job"
    },
    "properties": [
        {
            "id": "custom.hidden",
            "value": true
        }
    ]
}
]
},
"gridPos": {
    "h": 10,
    "w": 4,
    "x": 15,
    "y": 1
},
"id": 2,
"links": [
    {
        "targetBlank": true,
        "title": "",
        "url": "https://support2.filewave.net/filewave/reports/50/overview/"
    }
],
"options": {
    "cellHeight": "sm",
    "footer": {
        "countRows": false,
        "fields": "",
        "reducer": [
            "sum"
        ],
        "show": false
    },
    "showHeader": true,
    "sortBy": [
        {
            "desc": false,
            "displayName": "device_name"
        }
    ]
},
"pluginVersion": "10.3.1",
"targets": [
    {
```

```
        "datasource": {
          "type": "prometheus",
          "uid": "filewave_prometheus"
        },
        "editorMode": "builder",
        "exemplar": false,
        "expr": "filewave_inventory_query_50",
        "format": "table",
        "instant": true,
        "legendFormat": "{{device_name}}",
        "range": false,
        "refId": "A"
      }
    ],
    "title": "Unhealthy Defender Clients",
    "transformations": [],
    "type": "table"
  },
  {
    "collapsed": false,
    "gridPos": {
      "h": 1,
      "w": 24,
      "x": 0,
      "y": 11
    },
    "id": 12,
    "panels": [],
    "title": "Threat Detection and Issues",
    "type": "row"
  },
  {
    "datasource": {
      "type": "prometheus",
      "uid": "filewave_prometheus"
    },
    "description": "",
    "fieldConfig": {
      "defaults": {
        "color": {
          "mode": "thresholds"
        },
        "custom": {
          "align": "auto",
          "cellOptions": {
            "type": "auto"
          },
          "inspect": false
        },
        "mappings": [],
        "thresholds": {
          "mode": "absolute",
          "steps": [
            {
              "color": "green",
              "value": null
            },
            {
              "color": "red",
              "value": 80
            }
          ]
        }
      },
      "unitScale": true
    },
    "overrides": [
      {
        "matcher": {
          "id": "byName",
          "options": "Time"
        }
      }
    ]
  }
]
```

```
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "Value"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "query_name"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "job"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "device_name"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
      "id": "byName",
      "options": "__name__"
    },
    "properties": [
      {
        "id": "custom.hidden",
        "value": true
      }
    ]
  },
  {
    "matcher": {
```

```
        "id": "byName",
        "options": "instance"
    },
    "properties": [
        {
            "id": "custom.hidden",
            "value": true
        }
    ]
},
{
    "matcher": {
        "id": "byName",
        "options": "defender_threats_detected_fwcomp_pack"
    },
    "properties": [
        {
            "id": "displayName",
            "value": "Threat Detected"
        }
    ]
}
]
},
"gridPos": {
    "h": 9,
    "w": 19,
    "x": 0,
    "y": 12
},
"id": 13,
"links": [
    {
        "targetBlank": true,
        "title": "Show Details",
        "url": "https://support2.filewave.net/filewave/reports/57/overview/"
    }
],
"options": {
    "cellHeight": "sm",
    "footer": {
        "countRows": false,
        "fields": "",
        "reducer": [
            "sum"
        ],
        "show": false
    },
    "showHeader": true
},
"pluginVersion": "10.3.1",
"targets": [
    {
        "datasource": {
            "type": "prometheus",
            "uid": "filewave_prometheus"
        },
        "editorMode": "builder",
        "exemplar": false,
        "expr": "filewave_inventory_query_57",
        "format": "table",
        "instant": true,
        "legendFormat": "{{label_name}}",
        "range": false,
        "refId": "A"
    }
],
"title": "Detected Threats",
"type": "table"
},
```

```
{
  "collapsed": false,
  "gridPos": {
    "h": 1,
    "w": 24,
    "x": 0,
    "y": 21
  },
  "id": 6,
  "panels": [],
  "title": "Windows",
  "type": "row"
},
{
  "datasource": {
    "type": "prometheus",
    "uid": "filewave_prometheus"
  },
  "description": "",
  "fieldConfig": {
    "defaults": {
      "color": {
        "mode": "palette-classic"
      },
      "custom": {
        "axisBorderShow": false,
        "axisCenteredZero": false,
        "axisColorMode": "text",
        "axisLabel": "",
        "axisPlacement": "auto",
        "fillOpacity": 80,
        "gradientMode": "none",
        "hideFrom": {
          "legend": false,
          "tooltip": false,
          "viz": false
        },
        "lineWidth": 1,
        "scaleDistribution": {
          "type": "linear"
        },
        "thresholdsStyle": {
          "mode": "off"
        }
      },
      "mappings": [],
      "thresholds": {
        "mode": "absolute",
        "steps": [
          {
            "color": "green",
            "value": null
          },
          {
            "color": "red",
            "value": 80
          }
        ]
      }
    },
    "unitScale": true
  },
  "overrides": []
},
{
  "gridPos": {
    "h": 10,
    "w": 8,
    "x": 0,
    "y": 22
  },
  "id": 4,
```

```
"links": [
  {
    "targetBlank": true,
    "title": "",
    "url": "https://support2.filewave.net/filewave/reports/52/overview/"
  }
],
"options": {
  "barRadius": 0,
  "barWidth": 0.97,
  "fullHighlight": false,
  "groupWidth": 0.7,
  "legend": {
    "calcs": [],
    "displayMode": "list",
    "placement": "bottom",
    "showLegend": false
  },
  "orientation": "auto",
  "showValue": "auto",
  "stacking": "none",
  "tooltip": {
    "mode": "single",
    "sort": "none"
  },
  "xTickLabelRotation": 0,
  "xTickLabelSpacing": 0
},
"targets": [
  {
    "datasource": {
      "type": "prometheus",
      "uid": "filewave_prometheus"
    },
    "editorMode": "builder",
    "exemplar": false,
    "expr": "filewave_inventory_query_52",
    "instant": true,
    "legendFormat": "{{defender_defs_version_fwcomp_pack}}",
    "range": false,
    "refId": "A"
  }
],
"title": "Virus Defs Versions Windows",
"type": "barchart"
},
{
  "datasource": {
    "type": "prometheus",
    "uid": "filewave_prometheus"
  },
  "description": "",
  "fieldConfig": {
    "defaults": {
      "color": {
        "mode": "palette-classic"
      },
      "custom": {
        "axisBorderShow": false,
        "axisCenteredZero": false,
        "axisColorMode": "text",
        "axisLabel": "",
        "axisPlacement": "auto",
        "fillOpacity": 80,
        "gradientMode": "none",
        "hideFrom": {
          "legend": false,
          "tooltip": false,
          "viz": false
        }
      }
    }
  }
},
```

```
    "lineWidth": 1,
    "scaleDistribution": {
      "type": "linear"
    },
    "thresholdsStyle": {
      "mode": "off"
    }
  },
  "mappings": [],
  "thresholds": {
    "mode": "absolute",
    "steps": [
      {
        "color": "green",
        "value": null
      },
      {
        "color": "red",
        "value": 80
      }
    ]
  },
  "unitScale": true
},
"overrides": []
},
"gridPos": {
  "h": 10,
  "w": 9,
  "x": 8,
  "y": 22
},
"id": 9,
"links": [
  {
    "targetBlank": true,
    "title": "",
    "url": "https://support2.filewave.net/filewave/reports/54/overview/"
  }
],
"options": {
  "barRadius": 0,
  "barWidth": 0.97,
  "fullHighlight": false,
  "groupWidth": 0.7,
  "legend": {
    "calcs": [],
    "displayMode": "list",
    "placement": "bottom",
    "showLegend": false
  },
  "orientation": "auto",
  "showValue": "auto",
  "stacking": "none",
  "tooltip": {
    "mode": "single",
    "sort": "none"
  },
  "xTickLabelRotation": 0,
  "xTickLabelSpacing": 0
},
"targets": [
  {
    "datasource": {
      "type": "prometheus",
      "uid": "filewave_prometheus"
    },
    "editorMode": "builder",
    "exemplar": false,
    "expr": "filewave_inventory_query_54",
```



```

        "instant": true,
        "legendFormat": "{{defender_app_version_fwcomp_pack}}",
        "range": false,
        "refId": "A"
    }
],
"title": "Defender Version Windows",
"type": "barchart"
},
{
    "collapsed": false,
    "gridPos": {
        "h": 1,
        "w": 24,
        "x": 0,
        "y": 32
    },
    "id": 5,
    "panels": [],
    "title": "macOS",
    "type": "row"
},
{
    "datasource": {
        "type": "prometheus",
        "uid": "filewave_prometheus"
    },
    "description": "",
    "fieldConfig": {
        "defaults": {
            "color": {
                "mode": "palette-classic"
            },
            "custom": {
                "axisBorderShow": false,
                "axisCenteredZero": false,
                "axisColorMode": "text",
                "axisLabel": "",
                "axisPlacement": "auto",
                "fillOpacity": 80,
                "gradientMode": "none",
                "hideFrom": {
                    "legend": false,
                    "tooltip": false,
                    "viz": false
                },
                "lineWidth": 1,
                "scaleDistribution": {
                    "type": "linear"
                },
                "thresholdsStyle": {
                    "mode": "off"
                }
            },
            "mappings": [],
            "thresholds": {
                "mode": "absolute",
                "steps": [
                    {
                        "color": "green",
                        "value": null
                    },
                    {
                        "color": "red",
                        "value": 80
                    }
                ]
            }
        },
        "unitScale": true
    },

```

```
    "overrides": []
  },
  "gridPos": {
    "h": 10,
    "w": 8,
    "x": 0,
    "y": 33
  },
  "id": 3,
  "links": [
    {
      "targetBlank": true,
      "title": "",
      "url": "https://support2.filewave.net/filewave/reports/51/overview/"
    }
  ],
  "options": {
    "barRadius": 0,
    "barWidth": 0.97,
    "fullHighlight": false,
    "groupWidth": 0.7,
    "legend": {
      "calcs": [],
      "displayMode": "list",
      "placement": "bottom",
      "showLegend": false
    },
    "orientation": "auto",
    "showValue": "auto",
    "stacking": "none",
    "tooltip": {
      "mode": "single",
      "sort": "none"
    },
    "xTickLabelRotation": 0,
    "xTickLabelSpacing": 0
  },
  "targets": [
    {
      "datasource": {
        "type": "prometheus",
        "uid": "filewave_prometheus"
      },
      "editorMode": "builder",
      "exemplar": false,
      "expr": "filewave_inventory_query_51",
      "instant": true,
      "legendFormat": "{{defender_defs_version_fwcomp_pack}}",
      "range": false,
      "refId": "A"
    }
  ],
  "title": "Virus Defs Versions macOS",
  "type": "barchart"
},
{
  "datasource": {
    "type": "prometheus",
    "uid": "filewave_prometheus"
  },
  "description": "",
  "fieldConfig": {
    "defaults": {
      "color": {
        "mode": "palette-classic"
      },
      "custom": {
        "axisBorderShow": false,
        "axisCenteredZero": false,
        "axisColorMode": "text",
```

```

        "axisLabel": "",
        "axisPlacement": "auto",
        "fillOpacity": 80,
        "gradientMode": "none",
        "hideFrom": {
            "legend": false,
            "tooltip": false,
            "viz": false
        },
        "lineWidth": 1,
        "scaleDistribution": {
            "type": "linear"
        },
        "thresholdsStyle": {
            "mode": "off"
        }
    },
    "mappings": [],
    "thresholds": {
        "mode": "absolute",
        "steps": [
            {
                "color": "green",
                "value": null
            },
            {
                "color": "red",
                "value": 80
            }
        ]
    },
    "unitScale": true
},
"overrides": []
},
"gridPos": {
    "h": 10,
    "w": 9,
    "x": 8,
    "y": 33
},
"id": 8,
"links": [
    {
        "targetBlank": true,
        "title": "",
        "url": "https://support2.filewave.net/filewave/reports/53/overview/"
    }
],
"options": {
    "barRadius": 0,
    "barWidth": 0.97,
    "fullHighlight": false,
    "groupWidth": 0.7,
    "legend": {
        "calcs": [],
        "displayMode": "list",
        "placement": "bottom",
        "showLegend": false
    },
    "orientation": "auto",
    "showValue": "auto",
    "stacking": "none",
    "tooltip": {
        "mode": "single",
        "sort": "none"
    },
    "xTickLabelRotation": 0,
    "xTickLabelSpacing": 0
},

```

```
"targets": [
  {
    "datasource": {
      "type": "prometheus",
      "uid": "filewave_prometheus"
    },
    "editorMode": "builder",
    "exemplar": false,
    "expr": "filewave_inventory_query_53",
    "instant": true,
    "legendFormat": "{{defender_app_version_fwcomp_pack}}",
    "range": false,
    "refId": "A"
  }
],
"title": "Defender Version macOS",
"type": "barchart"
}
],
"refresh": "",
"schemaVersion": 39,
"tags": [],
"templating": {
  "list": []
},
"time": {
  "from": "now-6h",
  "to": "now"
},
"timepicker": {},
"timezone": "",
"title": "Defender Dashboard",
"uid": "c26006b5-0295-4ec0-9b54-3efd3d714a9f",
"version": 1,
"weekStart": ""
}
```

Related Content

Related Content

- [Microsoft Defender Recipe \(Win\)](#)
- [Microsoft Defender Recipe \(macOS\)](#)
- [Microsoft Defender Compliance Pack \(macOS\)](#)

🔄Revision #10

★Created 13 February 2024 14:45:54 by Josh Levitsky

✍Updated 15 February 2024 01:04:01 by Josh Levitsky